

EICAS Automazione S.p.A.

excellence and passion in automatic control design



Welcome to Innovation





excellence and passion in automatic control design

EICASLAB[™] Demo RT-emb

Just 1 Software Suite

Just 1 Project

ALL the design phases



Welcome to Innovation







excellence and passion in automatic control design

EICASLAB™ Demo RT-emb

The operative modes:

- Modeling and Like Real-time Simulation
- Rapid Control Prototyping (RCP)
 - RCP On Field sub-mode
 - Slow Motion sub-mode
- Target
 - Hardware-in-the-loop (HIL) sub-mode
 - Final Validation Test (FVT) sub-mode

EICAS Automazione S.p.A.



Welcome to Innovation





Summary

Slide contents:

- Overview
- Requirements
- Operative modes
 - Modelling and Like Real-time Simulation
 - Rapid Control Prototyping On Field and Slow Motion
 - Hardware-in-the-loop
 - Final Validation Test
- Further information

AS Automazione S.p.A.



Welcome to Innovation





excellence and passion in automatic control design

Overview

Example of a **complete control design development**, from the Simulation to the download to Final Target.

The application case is the *rotating table* of the EICASLAB DEMO.







Welcome to Innovation







ome to Innovation

+39 011 43 60 679

Via Vincenzo Vela, 27 10128 Torino - ITALY (IT) Tel. +39 011 56 23 798 +39 011 56 23 088

Overview

Not required

AS Automazione S.p.A.

RT-emb = Real-Time on an embedded system

- Focus on the <u>real-time operative modes</u>: Rapid Control Prototyping (RCP), Hardware-in-the-loop (HIL) and Final Validation Test (FVT)
- Allows the user to experiment the Target mode <u>on a</u> <u>popular embedded system</u> (e.g. Raspberry Pi)



excellence and passion in automatic control design

Overview The EICASLAB RCP Platform

Standard multi-core PC equipped with a Real-Time Operative System (RTOS) and the EICASLAB Suite

RCP=Rapid Control Prototyping

AS Automazione S.p.A.



It is used to run EICASLAB, execute real-time tasks, to cross-compile the code for the embedded board and program it.

Welcome to Innovation





Overview

There are two versions of the RT-emb demo for different hardware devices:

- BeagleBone Black board (BBB) version,
- Generic Linux Target version (e.g. Raspberry Pi).

Both of them do not require real plant, as RT-PC demo.





excellence and passion in automatic control design

Minimum requirements (PC)

This demo requires real-time performance, therefore it is only available in Linux version.

- Dual core CPU
- 2 GB of RAM

S Automazione S.p.A.

- 1 GB of disk space
- GNU/Linux operative system



rt.wiki.kernel.org

- PREEMPT_RT kernel configuration (recommended)
- Networking interface to connect to the target (USB2.0 or Ethernet for BBB, Ethernet or WiFi for other boards)





Minimum requirements (embedded)

EICAS Automazione S.p.A.

Requirements for the embedded board:

- 512 MB of RAM
- 100 MB of storage space
- GNU/Linux operative system with GCC
- PREEMPT RT kernel configuration (mandatory)
- Networking interface to connect to PC, SSH server

The demo was tested on **BeagleBone Black** and **Raspberry Pi 3**. For further information and how-to: read demo user manual, or mail to support@eicaslab.com Welcome to Innovation

AS Automazione S.p.A.



Minimum requirements (projects)

The EICASLAB Demo RT-PC includes three projects in the **DEMO** menu of the MASTER tool:

- the first with the pre-designed control algorithm by EicasLab Automatic Algorithm Generation (AAG)
- the second with an empty control where the user can program his own algorithm
- the third is a "real-time plant emulator" which is used in a second instance of the demo program during Rapid Control Prototyping and Final Validation Test trials, as explained in the following.

S Automazione S.p.A.

Welcome to Innovation





The control objective

- Impose the desired trajectory to a rotating table
- Actuator: electric motor acting on the rotating table
- Sensor: one encoder measuring motor angle







EICAS Automazione S.p.A.

excellence and passion in automatic control design

Rotating Table Physical Model



Welcome to Innovation





excellence and passion in automatic control design

Modelling and Like Real-time Simulation

The Modelling and Like Real-time Simulation mode allows the user to design and test the control algorithm and simulate the Rotating Table response to its commands.



Welcome to Innovation





Modelling and Like Real-time Simulation

The main M&LRTS mode purposes are:

- to model the plant
- to run and to validate the model
- to design the control algorithm
- to run and to validate the algorithm against

the simulated plant

AS Automazione S.p.A.

Welcome to Innovation





excellence and passion in automatic control design

Modelling and Like Real-time Simulation

Who does what in Modeling and Like Real-time Simulation operative mode in RT-emb demo:

HW	EICASLAB RCP Platform	Embedded board target	Rotating Table emulator
SW	run control logic	unused	unused
	simulate the plant		

Welcome to Innovation





EICAS Automazione S.p.A.

excellence and passion in automatic control design

Modelling and Like Real-time Simulation



Fax +39 011 43 60 679



Modelling and Like Real-time Simulation

The **SIM tool** allows the user to control the execution of simulation trials, providing diagrams, editing of run-time parameters and storage of data for post-analysis with the POST tool.

EICAS Automazione S.p.A.



Welcome to Innovation





excellence and passion in automatic control design

Rapid Control Prototyping

The Rapid Control Prototyping operative mode allows the user to test the control algorithm under development directly on the real **plant** using the advanced (and comfortable) analysis, debug and recording tools available on the EICASLAB RCP Platform. It includes two operative submode: RCP On Field and Slow Motion.



Welcome to Innovation





Rapid Control Prototyping

The main RCP operative mode purposes are:

- to run and validate the algorithm against the real plant
- to monitor, record and tune real physical quantities

and parameters

AS Automazione S.p.A.

to use debug and slow motion tools provided by the

EICASLAB RCP Platform

Welcome to Innovation





excellence and passion in automatic control design

RCP On Field

In **RCP On Field** operative sub-mode, EICASLAB runs the control as a real-time application, interfacing with the **real plant** through a set of I/O interfaces, created by EICASLAB Automatic Code Generation (ACG).

Rapid Control Prototyping scenario

Control algorithms



Welcome to Innovation





excellence and passion in automatic control design

RCP On Field

The **project layout** in this sub-mode:



The System Layout of the Rotating Table project in RCP shows that all blocks except the *Processor* are **disabled**.

Welcome to Innovation





RCP On Field

In this demo, the user can explore the system layout, its pre-defined configuration and the set of parameters for the RCP trial, then generate the real-time application.



Welcome to Innovation







excellence and passion in automatic control design

RCP On Field

The **project layout** in this sub-mode:



Since the real rotating table is not available and we must close the loop, it will be simulated by using a separate project as real-time emulator.

Welcome to Innovation





RCP On Field

Who does what in RCP On Field operative sub-mode in RT-emb demo:

HW	EICASLAB	Embedded	Rotating Table
	RCP Platform	board target	emulator
SW	run control logic	unused	simulated by second project

Welcome to Innovation







RCP On Field

The two projects in two EICASLAB instances



Welcome to Innovation







escellence and possion

atic centrel de

in autor

EICAS Automazione S.p.A.

excellence and passion in automatic control design

RCP On Field

The **RCP Manager tool** includes a GUI for controlling the execution of the real-time program and providing timing diagrams, performance reports and other functions. RCP Manager Settings Modify Parameters Copy Output



Welcome to Innovation





excellence and passion in automatic control design

RCP On Field



EICAS Automazione S.p.A.

Tel. +39 011 56 23 798 +39 011 56 23 088 Fax +39 011 43 60 679



Slow Motion

The **Slow Motion operative sub-mode** is an offline **replay** of the algorithm execution, using data recorded during the previous RCP trials.



EICAS Automazione S.p.A.

Repeat the trial as a MOVIOLA with EICASLAB[™]



Welcome to Innovation





Slow Motion

Who does what in Slow Motion operative sub-mode in RT-emb demo:

HW	EICASLAB	Embedded	Rotating Table
	RCP Platform	board target	emulator
SW	run control logic	unused	unused

simulated plant from recorded data

EICAS Automazione S.p.A.

Welcome to Innovation





Slow Motion

The **Slow Motion tool** includes a GUI for managing the execution of the replay of trials recorded on field, providing timing diagrams and other functions.





excellence and passion in automatic control design

Target

The Target operative mode allows the user to export the control algorithm to the final hardware device that will execute it to control first the simulated plant in Hardware-inthe-loop and then the real plant in Final Validation Test submodes.



Embedded board (target)

Welcome to Innovation





excellence and passion in automatic control design

Target

The Target operative mode allows the user to export the control algorithm to the final hardware device that will execute it to control first the simulated plant in Hardwarein-the-loop and then the real plant in Final Validation Test sub-modes.



Welcome to Innovation





Target

EICASLAB provides the routines to generate the *Basic Software,* not only for the EICASLAB RCP Platform itself, but also for a family of devices or for a specific hardware architecture.

ACG means Automatic Code Generation





excellence and passion in automatic control design

Target

This demo is designed to show EICASLAB in action on an external embedded systems: the ACG output is automatically transferred on it using SSH and compiled by GCC.



Welcome to Innovation





excellence and passion in automatic control design

Target

This demo includes HIL and FVT operative modes, so the ACG for target is repeated twice to build two different real-time applications on the remote embedded target.



Welcome to Innovation





excellence and passion in automatic control design

Hardware-in-the-loop

The Hardware-in-the-loop operative sub-mode allows to test the control algorithm execution on the target hardware against a simulated plant executed in real time on the EICASLAB RCP Platform.



Welcome to Innovation





excellence and passion in automatic control design

Hardware-in-the-loop

Who does what in Hardware-in-the-loop operative submode in RT-emb demo:

HW	EICASLAB	Embedded	Rotating Table
	RCP Platform	board target	emulator
SW	simulates plant	runs control logic	unused







Hardware-in-the-loop

The **project layout** in HIL sub-mode:



Welcome to Innovation







excellence and passion in automatic control design

Hardware-in-the-loop

When the demo is in HIL operative sub-mode, the user can see differences with respect to RCP: the plant is enabled for simulation and the processor is assigned to target.







excellence and passion in automatic control design

Hardware-in-the-loop

The **HIL Manager** includes a GUI for managing the execution of the real-time plant simulator program, similarly to RCP Manager for RCP operative mode.



Welcome to Innovation





Hardware-in-the-loop



Via Vincenzo Vela, 27 10128 Torino - ITALY (IT) Tel. +39 011 56 23 798 +39 011 56 23 088 Fax +39 011 43 60 679



EICAS Automazione S.p.A.

escellence and p



excellence and passion in automatic control design

Final Validation Test

The Final Validation Test operative submode allows the user to test the control algorithm execution on the target hardware controlling the real plant.

EICAS Automazione S.p.A.

Final Validation Test scenario



Welcome to Innovation





excellence and passion in automatic control design

Final Validation Test

The monitoring and run-time tuning are provided exploiting the real time execution features by the EICASLAB RCP Platform.

Target Real plant **High level and** mission commands, parameters erfaces **EICASLAB** 0 RCP Platform Data monitoring & recording Linux R

Welcome to Innovation

Via Vincenzo Vela, 27 10128 Torino - ITALY (IT) Tel. +39 011 56 23 798 +39 011 56 23 088 Fax +39 011 43 60 679



EICAS Automazione S.p.A.

Final Validation Test scenario



excellence and passion in automatic control design

Final Validation Test

Who does what in Final Validation Test operative submode in RT-emb demo:

HW	EICASLAB	Embedded	Rotating Table
	RCP Platform	board target	emulator
SW	monitoring supervisor	runs control logic	simulated by second project

Welcome to Innovation





Final Validation Test

The project layout in this mode:



The system layout shows that the *Plant Area* is disabled again, because during the FVT trials the **real plant** is simulated using a separate project.

Welcome to Innovation







Final Validation Test

The project layout in this mode:



Welcome to Innovation







excellence and passion in automatic control design

Final Validation Test

Similarly as done in RCP On Field, this demo works without real plant: the user has to run the plant emulator in a second instance of EICASLAB demo.



Welcome to Innovation





auralience and e

EICAS Automazione S.p.A.

excellence and passion in automatic control design

Final Validation Test

The **TARGET Manager** includes a GUI for managing the execution of the real-time FVT program, similarly to RCP Manager and HIL Manager.



Welcome to Innovation





excellence and passion in automatic control design

Final Validation Test





Further readings

About this demo:

- EICASLAB Demo RT-emb Webinar
- EICASLAB Demo RT-emb User Manual
- Rotating table technical note

About EICASLAB :

AS Automazione S.p.A.

- EICASLAB User Manual
- Other EICASLAB Webinars

Welcome to Innovation





excellence and passion in automatic control design

The demo installer is downloadable from EICASLAB website (<u>www.eicaslab.com</u>)



For more info, please contact: <u>support@eicaslab.com</u>



Welcome to Innovation



